

# Configure Single Sign-on (SSO) with Ping Identity

How to set up SAML SSO authentication with the Ping Identity application.

Document generated 07/29/2025

#### **PDF VERSION**

Tags | Authentication | SAML | SSO | Ping |

Applies to: Free Basic Business Enterprise

#### **ADMIN PRIVILEGES REQUIRED**

This documentation is for **Stack Overflow for Teams Enterprise**. Free, Basic, and Business users can access their documentation here. Find your plan.


#### Overview

The following instructions describe how to integrate your Stack Overflow for Teams Enterprise (SOE) instance and the Ping Identity application. Once configured, your users will be able to use Ping Identity's Security Assertion Markup Language (SAML) for Single Sign-on (SSO) authentication into your site.


**NOTE:** As you work through these steps, it's helpful to have your SOE Authentication admin settings page open in one browser tab and the Ping Identity admin page open in another.

# Create the Stack Overflow Application in Ping Identity


1. From the "Your Environments" dashboard in Ping Identity, click **Administrators**.




- 2. Click Connections, then Applications.
- 3. Click the (+) button.



- 4. Create the application profile by entering the following:
  - Application name A unique identifier for the application (Stack Overflow).
  - Description (optional) A brief description of the application.
  - **Icon (optional)** A graphic representation of the application. The image file can be .jpg, .jpeg, .gif, or .png format, up to 1MB in size.
- 5. Choose **SAML Application** as the Application Type.



- 6. Click Configure.
- 7. Select **Manually Enter**.
- 8. Enter the ACS URL (the "Assertion consumer service URL" value found on your SOE Authentication page).
- 9. Enter the Entity ID (the "Issuer" or "Audience Restriction" value found on your SOE Authentication page).



- 10. Click Save.
- 11. Ping Identity creates new applications in a disabled state. Click the **toggle button** to the right of your application to enable it.



# Set up SOE

12. Copy the **Single Signon Service URL** from the Ping Identity "Configuration" tab. Paste the URL into the **SSO Service URL** field on the SOE Authentication page.

**NOTE:** PingOne for Enterprise doesn't provide the **Single Signon Service URL**. Instead, Ping provides instructions for how to manually create an SSO Service URL.

- 13. On the SOE authentication settings page, uncheck **Use Subject/NameID as user identifier**. Insert "saml\_subject" as the **User identifier assertion**. This is a required field for Ping Identity.
- 14. Add required assertions for the user display name and the user email. We recommend "displayName" and "emailAddress" respectively.

## User identifier assertion

e.g., http://schemas.microsoft.com/identity/claims/objectidentifier, uid, login, objectGUID

saml\_subject

# Display name assertion

e.g., http://schemas.microsoft.com/identity/claims/displayname, displayName

displayName

### **Email address assertion**

e.g., http://schemas.xmlsoap.org/ws/2005/05/identity/claims/emailaddress, email, emailAddress

emailAddress


## **Optional items**

### Job title and department user assertions

You can use the same process to add the optional **Job Title** and **Department** assertions. If Stack Overflow for Teams detects these assertions in the SAML data on login, it automatically updates the corresponding user data fields. Adding these two optional assertions also allows you to use Stack Overflow for Teams' Connectivity reporting feature.

#### **Automatic certificate updates**

To maintain security, certificates must be updated regularly. Automating this task increases site security, reduces technical workload, and eliminates downtime caused by expired certificates. To enable optional automated certificate updates, select and copy the IDP Metadata URL on Ping Identity under the **Configuration** tab. (You can also click the **two pieces of paper** button to copy the URL to your clipboard.)



Paste the Ping IDP Metadata URL into the **Update certificates from federation metadata** field on the SOE Authentication page. If your SOE site can successfully access the IDP Metadata URL, it will automatically update security certificates.



# Set up SOE (continued)

15. On the Ping Identity page, click **Download Signing Certificate**.



16. On the SOE Authentication page, click **Add another certificate**. Paste the signing certificate into the **Identity provider certificates** field.

#### Identity provider certificates

Base64-Encoded public keys, used to verify SAML responses from the identity provider

MIIDejCCAmKqAwlBAqIGAYoo/qXIMA0GCSqGSib3DQEBCwUAMH4xCzAJBqNVBAYTAIVTMRYwFAYDVQQKDA1QaW5nIElkZW50aXR5MRYwFA DVQQLDA1QaW5nlElkZW50aXR5MT8wPQYDVQQDDDZQaW5nT25llFNTTyBDZXJ0aWZpY2F0ZSBmb3lgQWRtaW5pc3RyYXRvcnMgZW52aXJv m1lbnQwHhcNMjMwODI0MTkyMTMxWhcNMjQwODIzMTkyMTMxWjB+MQswCQYDVQQGEwJVUzEWMBQGA1UECgwNUGluZyBJZGVudGl0e EWMBQGA1UECwwNUGluZyBJZGVudGl0eTE/MD0GA1UEAww2UGluZ09uZSBTU08gQ2VydGlmaWNhdGUgZm9yIEFkbWluaXN0cmF0b3JzIGVu mlyb25tZW50MIIBljANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEAn9YH1bZPGJjYSWSB3ZB8wYsmUSEN6BM3jJqHdJggQvX+ohG66zGsn0Z lkf4T21FnhGVGqQPh2rRM1EJ9qn1vX9BdeqyN0qVb5lBPiPWCRTeR1Xnnle/bJOCrOZnnXwwSVCKt38+DMv1cb1jeEO5G+U4oJUt0Ww9vnmP+Se wMkA7ff7UeQawpBuBr+dD1ksCY33fZ9CycDp+7DL7GcNt0g/YfawCudfbVe2WqohuRthqOSBdBzwfCtMVZkUC9LJiXMkIXoCo5o6meBxeEU4yUn yOWuEAcnAzHAomZFtkhZpxqa+irTS1Ec7nxhZMdA4o0qd1EQUIETUMq1KSR/BQIDAQABMA0GCSqGSIb3DQEBCwUAA4IBAQAmyRM2IXyo/vfFI OB9IXdauZ3P0xCLSU6+6Z6YgWbk4ZFqTV3zEaw9OU0X7sCkK5KcXVCj2R1Gj60fA9OMR5iBZYX2WaH8LbiyINttJjCQHhpiU5DuKe6cLDyVwNbu6n mnFCIWvBoLDE0OVbvUYyMX8roCdpy+lns3TazJqxtx9P0E0wdR34ZQ5QggwAZ/W6BB8MrJwxOzNMbZd+rEPPceayn0X5

Validate Certificate Remove Certificate

17. Click Validate Certificate. If successful, a green notification will appear with information about the certificate.

# **Identity Provider Certificates**

Base64-encoded public keys used to verify SAML responses from the Identity Provider

----BEGIN CERTIFICATE----

MIID/zCCAuegAwlBAgIULrV2f2K1h6c2MrEbX35VMi7sNMwwDQYJKoZIhvcN

DOAWLIDEHADLOALLECAWELISDHY2caT27lam7ch2caE\AFiADLlwEwVD\O



Cancel

Issuer: CN="Ping Identity Account", OU=Ping Identity IdP, O=Stack Overflow Inc Subject: CN="Ping Identity Account", OU=Ping Identity IdP, O=Stack Overflow Inc

Valid: Apr 11 2023 to Apr 11 2028

Thumbprint: 0123456789ABCDEF0123456789ABCDEF

SignatureAlgorithm: sha1RSA

If your certificate is not valid, SOE will display a red alert: "Could not parse certificate".

# Identity Provider Certificates

Base64-encoded public keys used to verify SAML responses from the Identity Provider

----BEGIN CERTIFICATE----

MIID/zCCAuegAwlBAgIULrV2f2K1h6c2MrEbX35VMi7sNMwwDQYJKoZlhvcN AQEF

POAMLIDEHMPLCALLECAMELI2DHV2caT27lom7ch2caEMEiMDLlwEwVDVO



S Validate certificate

Cancel


Could not parse certificate

## Map SAML attributes

18. Return to Ping Identity, and go to the "Attribute Mappings" tab. Edit the mappings by clicking the **blue pencil**. Add one name attribute and one email attribute to the PingOne column (for example: Given Name and Email Address). Set

the Stack Overflow values to match those on the SOE Authentication page.

If you're using the optional job title and department assertions, set those here as well.




# Complete and test setup

19. On the SOE Authentication page, click **Authenticate and enable**. A green "SSO successfully enabled" alert will appear at the top of the page.

To confirm successful SSO setup, try signing into your SOE site by opening the site URL in a new incognito tab (or a different browser). If the login works, your SSO setup is complete.

# **Troubleshooting**

SOE has a SAML troubleshooting page that contains helpful info if you experience problems with your SAML setup. To enable this page, check the **Enable SAML login troubleshooting page** checkbox under the "Additional Options" heading. This reveals the **Test currently saved SAML configuration** button.



Click **Test currently saved SAML configuration** to see the SAML troubleshooting page. You can also click the /enterprise/support/saml-login link under the **Enable SAML login troubleshooting page** option.

If the SAML connection fails, the troubleshooting page will allow you to inspect the SAML response for issues with attribute mapping (or other problems). Here's an example of the SAML login troubleshooting page report:

```
Trying to get the User Identifier from NameID
!!! Unrecognized or missing NameID Format. !!!
!!! Please make sure that the NameID is stable across logins. !!!
NameID Value: 01234567-89ab-cdef-0123-456789abcdef
AttributeValue for 'displayname': Jim Berry
AttributeValue for 'emailaddress': jberry@berrygood.com
```